Pointed

A Robert Kaufman Pattern

From background fabric (Kona Snow) cut (included in packet):

- 4 squares at 3" x 3" from 12 1/2" piece
- 4 squares at 2 1/2" x 2 1/2" from 10 1/2" piece
- 1 piece at 2 1/2" x 8 1/2" for top sashing

From your print fabric cut: 4 squares at 3" x 3"

Step 1: Pair a 3" background square with a 3" print square, RST. Mark a diagonal line on the wrong side of one square. Sew 1/4" away from both sides of the marked line. Cut on the marked line, creating two half-square triangles (HSTs). Press toward the darker fabric. Trim to 2-1/2" square.




Repeat to make 8 HSTs.

Step 3: Gather:

four 2-1/2" Fabric A squares eight A/B HSTs

Arrange the units into three rows of four. Note the fabric placement and block orientation in the Block Assembly Diagram.

Step 4: Sew the squares together to form the rows. Press the seams in opposite directions every other row.



Step 5: Sew the rows together,


nesting the seams and pressing the seams to one side to form the block. The block should measure 6-1/2" x 8-1/2".

Step 6: Sew a 2 1/2" x 8 1/2" sashing strip to the "top" of the block.

Finished block should measure 8 1/2" x 8 1/2"

PointedA Robert Kaufman Pattern

Step 7: Arrange the Blocks together as indicated in the Quilt Assembly Diagram, noting the fabric placement and block orientation. Sew each column together, using background sashing strips(cut 1 1/2") between each block and at the beginning OR end of each column. Press seams toward the sashing. Repeat to make six block columns.



Step 8: Sew the column sashing

and block rows together. Press seams open or to the sashing. Sew the top/bottom border to the quilt. Press.

This is a free pattern which can be downloaded from: robertkaufman.com